
STARS USER MANUAL..... 1

STARS DESCRIPTOR TABLE D66 – OPERATOR CLASS 1

D66 – OPERATOR CLASS.....1

D66 – OPERATOR CLASS, DATA ENTRY REQUIREMENTS.....1

STARS USER MANUAL

STARS DESCRIPTOR TABLE D66 – OPERATOR CLASS

D66 – OPERATOR CLASS

The D66 table identifies the valid ranges of transaction codes that each operator class type can input into STARS. STARS requires an operator class on each user security.

VERSION 3.1	STARS--DESCRIPTOR TABLE MAINTENANCE/INQUIRY	S023
FUNCTION: R (A=ADD, C=CHANGE, D=DELETE, N=NEXT, R=RECALL)		
TABLE-ID-NUMBER: 66 OPERATOR CLASS		
.....1.....2.....3.....4.....5		
TABLE-ENTRY-KEY: 131		
OPERATOR CLASS		
REFERENCE-DATA: I027,100-195,400-499,549-599		
INCLUDE/EXCLUDE		
TITLE: REVENUES, RECEIPTS, GRANT AND TRANSFER		
EFF-START-DATE:	EFF-END-DATE:	LAST-PROC-DATE: 123097

D66 – OPERATOR CLASS DATA ENTRY REQUIREMENTS

<u>Data Element</u>	<u>Description</u>
TABLE-ID-NUMBER	Enter 66 .
TABLE-ENTRY-KEY	<u>OPERATOR CLASS</u> Enter the two-digit operator class assigned by SCO, and the one-digit multiple page indicator. If the reference data field is full on the first page (indicator “1”) and requires another screen, this page indicator would be “2” for the second screen.

Data Element	Description
REFERENCE DATA	<p><u>INCLUDE/EXCLUDE</u></p> <p>Enter the one-character include/exclude indicator:</p> <p>I – Include input capabilities for the following transaction code ranges.</p> <p>E – Exclude input capabilities for the following transaction code ranges.</p> <p>Enter the three-character transaction code separated by either a comma (to show a break between the transaction code ranges) or a hyphen (to show the “to”-“from” transaction codes in a range).</p>
TITLE	<p>Enter the title of the operator class, up to 50 characters, to identify the types of transaction code ranges. (E.g., includes revenues, receipts, Grants and transfers)</p>